



DMS Integration Guide
Ford Europe

Contents


Introduction	2
Install the DMSi application	3
Configure the DMSi for multiple applications	4
Set up DMS integration with Microcat EPC	5
Set up a new DMS connection	5
Configure the DMSi Integration Settings	8
Configure the DMS Pricing	9
Log in to the DMS	10
View the part information	12
Transfer parts to the DMS	13
Set up DMS integration with Superservice Menus	14
Set up a new DMS connection	14
Configure the DMSi Integration Settings	17
Log in to the DMS	18
View DMS pricing options	20
Transfer service information to the DMS	20
Manage integration settings	21
Delete a connection	21
Edit a connection	21
Export or import a connection	21

Introduction

Infomedia products have the ability to integrate with your Dealer Management System (DMS) using the Infomedia DMSi application. Transferring parts directly to your DMS saves time, reduces errors and streamlines operations within your dealership.

This guide is divided into the following sections:

- Install the DMSi application
- Configure the DMSi for multiple applications
- Set up DMS Integration with Microcat EPC
- Set up DMS Integration with Superservice Menus
- Manage integration settings



- ▶ For more information on DMS integration, contact Customer Service:
<https://www.infomedia.com.au/contact/customer-support>.

Install the DMSi application

The Infomedica DMSi must be installed and configured to enable the integration between Infomedica products and the DMS. The application setup is a 1-click installation that will allow auto-updating when new versions are released.

The application can be installed locally on each computer or centrally on a server depending on the dealer's requirements. The Infomedica DMSi requires the Microsoft .NET framework (latest version) and will automatically include the Microsoft .NET framework in the DMSi installation, if required.

To install the Infomedica DMSi:

- 1 Go to this website: <https://dmsi.autopartsbridge.com/ui/DMSi/publish.htm>.
- 2 Select the language from the drop-down and click **Install**.

The Infomedica DMSi application will be downloaded.


- 3 Click the DMSi file to open it and start the installation.
- 4 Click **Install**.

The installation may take several minutes.

- 5 When prompted, enter your user name and password.

Use the same login credentials that you use to log into Microcat EPC or Superservice Menus.

- 6 Click the **Save login details** checkbox and then click **OK**.



DMSi Login

Please enter your Infomedica credentials to allow the DMSi to connect to the server.

User name: user@dealer.com

Password: *****

Save login details

Cancel OK

Configure the DMSi for multiple applications


The DMSi can be configured to support connections from multiple Infomedia applications, such as multi-franchise versions of Microcat EPC. When you set up a DMSi connection, the User ID field will be filled out automatically.

Where dealerships are using advanced integration protocols such as web services and batch file, the DMSi application can be configured on a server to support multiple user connections.

To configure the DMSi for multiple applications:

- 1 Add a new preconfigured or customised connection as described above or access the settings of an existing DMS connection.
- 2 Select the **Advanced Settings** checkbox and type a user ID, if required.

The User ID field will be automatically filled when you set up a DMSi connection.



The image shows a screenshot of a software interface. At the top, there is a header 'Advanced Settings' in bold. Below it, there is a label 'User ID' followed by a text input field. The input field contains the text 'pelvy'.

- 3 Click **OK**.
- 4 Add additional connections as required.

Set up DMS integration with Microcat EPC

Once the DMSi has been installed, you can set up a DMS connection in the DMSi and then configure the integration settings within Microcat EPC.

Depending on the connection type you select when you log in, Superservice Menus can then exchange data with your DMS and transfer parts and service information to your DMS.


Set up a new DMS connection

The Infomedia DMSi allows you to add either preconfigured or customised DMS connections.

Add a preconfigured DMS connection

If the settings for your preferred DMS connection have been automatically preconfigured in the DMSi, the DMS connection will be available in the Preconfigured connections frame.


To add a preconfigured DMS connection:


- 1 Right-click the **DMSi** icon  on the Windows taskbar and select **Settings**.
- 2 Click **Add New**.
- 3 Select **Microcat EPC – Ford Europe** from the **Select application** drop-down.
- 4 Select your DMS from the **Use a preconfigured connection** drop-down and click **OK**.
- 5 Double-click on your new DMS connection in the Available Connections frame.
- 6 Click **Settings** and confirm details or make changes, as required.
- 7 Click **OK**.

Add a custom DMS connection

The Infomedia DMSi allows you to add customised DMS connections.

To add a custom connection for a web services-based DMS:

- 1 Right-click the  icon on the Windows taskbar and select **Settings**.
- 2 Click **Add New**.
- 3 Select **Microcat EPC – Ford Europe** from the **Select application** drop-down.
- 4 Click **Add New** in the **Set up a custom connection** frame.
- 5 Select **Integrate with a Web-Services-based DMS** and click **Next**.
- 6 Specify the web services settings in the **General** tab.
By default, **FCSD-E** will be selected automatically as the provider.
- 7 Enter the **DMS Name**, **URL** and **URN** in the **Provider Settings** fields.



New DMS Configuration Wizard

Web Services Settings
Please select your Web Services settings.

General

Select Provider

FCSD-E

Provider Settings

DMS Name
Ford DMS


URL
http://localhost:7070/axis/services

URN
DMSServer

Test Connection

Back Next Cancel

The information can be copied from Ford eCat (**More** → **Settings** → **Administration tab** → **DMS Server**) or supplied by the Dealer Service Provider (DSP).




Set DMS Parameters

URL http://127.0.0.1:0000

URN DMSServer

- 8 Click **Test DMSi Connection** to ensure a successful connection with the DMSi.
If you are unable to connect, check your settings.
- 9 Once your settings are complete, click **Next**.
- 10 Confirm the name or type a new name for the DMS connection and click **Finish**.
By default, the DMS name entered in the Provider Settings will be displayed.



New DMS Configuration Wizard

Finished

You have successfully configured your new DMS connection.

Type a name you want for this connection:

Ford DMS (FCSD-E)


To edit this connection later, select the connection from the Selected Connections list and click the Settings button.

Click Finish to add this configuration to your selected DMS connections.

Back Finish Cancel

- 11 Click **OK**.

The new DMS connection will be displayed in the Available Connections panel of the Integration Settings window in the DMSi.



- ▶ To check your DMSi settings at any time, right-click the Infomedia DMSi 8  icon on your Windows taskbar and select **Settings**.

Configure the DMSi Integration Settings

Once the DMSi is installed, you need to check and configure the DMSi settings within Microcat EPC.

New and previous DMSi connections will be displayed in the Available Connections drop-down within the Integration tab of the Settings window.

To set up the DMSi integration within Microcat EPC:

- 1 Access Microcat EPC, click the  icon and select **Settings**.
- 2 Select the **Integration** tab and view your DMSi Integration settings.
- 3 Click the **New DMSi Application** icon  to activate the new DMSi.
- 4 Select **Local** from the **DMSi Integration Type** drop-down.
- 5 Select your DMS connection from the **Available Connections** drop-down.
If you have multiple DMS connections, you must select the required connection.
- 6 Click **Test Connection** to check that the connection to the DMSi is successful (if required).

When you select your connection, an automatic test is performed.

- 7 Enter your DMS user name and password.

Your DMS credentials are different from your Microcat EPC credentials.

- 8 Select the **Automatic Logon** checkbox.

If the checkbox is not selected, you will be prompted to enter the DMS credentials each time you logon.

DMSi Integration

Enable Integration

DMSi Integration Type
Local

Available Connections
Ford Europe (FCSD-E)

DMS Credentials

User Name
A1B23C456D


Password
.....

Automatic Logon

Configure the DMS Pricing

You can select the default pricing source to use when ordering parts, such as Microcat Pricing or DMS Pricing. The DMS Pricing option will only be listed in the drop-down if you have already set up the DMSi and have connected to the DMS.

To set up the DMS pricing within Microcat EPC:

- 1 In Microcat EPC, click the  icon and select **Settings**.
- 2 Select the **General** tab in the Settings window.
- 3 Select **DMS Pricing** from the **Pricing Source** drop-down.
- 4 Select the price level from the **Default Pricing Level** drop-down.

This will be the price level used when ordering parts.



Price Display Selection

Pricing Source
DMS Pricing

Default Pricing Level
Customer

Retail
Dealer
Customer
Hide Pricing

- 5 Close the Settings window.

Log in to the DMS

Once your settings are complete, you can log in to the DMS from Microcat EPC. You will then need to select a connection type. There are three types of connection to the DMS.


Connection Type 1 - Default

- This connection type uses no customer or vehicle information from the DMS. The vehicle is selected within Microcat EPC.
- It allows only part and fluid information lookups from the DMS, without any customer-specific pricing.
- This connection type does not allow you to transfer an order to the DMS.


Connection Type 2 - Current DMS Session

- This connection type uses customer or vehicle information from an open session within the DMS.
- The list of results will be displayed, allowing you to select one.
- The information about the selected customer and vehicle will be loaded.
- This connection type allows you to transfer an order to the DMS.

Connection Type 3 - Microcat EPC Session

- This connection type allows you to search the DMS for customer or vehicle information.
 - The list of results will be displayed, allowing you to select one.
 - The information about the selected customer and vehicle will be loaded.
 - This connection type allows you to transfer an order to the DMS.
- ▶ To change the type of connection to your DMS, click the  icon.

To log on to the DMS and select the connection type:

- 1 Click the  icon on the status bar.
When successfully connected, the DMS icon will display as green.
- 2 Select your connection type and click **Connect**:
 - **Default (No Parameters)**: There is no further action for this option.
 - **Current DMS Session**: After you click Connect, a list of your current open sessions will be displayed.
 - **Microcat EPC Session**: Enter your search criteria, such as the customer name or VIN, to perform a search on the DMS. If any customer details are already loaded, they will automatically populate the customer or vehicle information.

DMS Connection Type
✕

Please select a DMS connection type:

1. Default (No Parameters)
 2. Current DMS Session
 3. Microcat EPC Session

- 3 Select the customer record that you want from the list (if required).
The customer and vehicle information will be loaded.

View the part information

In Microcat EPC, when you view the Part Data Card a DMS tab will be displayed. When the DMS is connected, you can view the part information, the DMS stock and the pricing details.

If the Current DMS Session or the Microcat EPC Session connection types were selected, then customer-specific pricing will also be shown (if available).

To view the part data from the DMS in Microcat EPC:

- 1 In Microcat EPC, navigate to a section illustration.
- 2 Click the callout in the illustration or the part number in the list to display the Part Data Card.
- 3 Click the **DMS** tab on the Part Data Card.



- 4 View the part information.
- 5 View the customer-specific pricing information in the **Customer (exc. VAT)** and **Customer (inc. VAT)** fields.
- 6 View the **Bin Location** and **SOH** details.


Transfer parts to the DMS

The Order screen will automatically be updated with the DMS pricing and stock details (if the DMS pricing source is selected in the Settings window).

If the Current DMS Session or the Microcat EPC Session connection types were selected, you can transfer parts information from Microcat EPC to your DMS.

To transfer parts from Microcat EPC to the DMS:

- 1 In Microcat EPC, add parts to the order.
- 2 In the **Order Details** tab, select **DMS Pricing** in the **Pricing Source** drop-down and select **Customer** in the **Price Level** drop-down (if required).



The screenshot shows the 'Order Details' form with the following fields and values:


- DMS Document Number: [Empty text box]
- PO/Estimate No.: [Empty text box]
- Notes: [Empty text area with a double-slash icon]
- Pricing Source: **DMS Pricing** (selected in a dropdown menu)
- Price Level: **Customer** (selected in a dropdown menu)

- 3 View the part details in the Order screen.

The information about parts, SOH and pricing will be updated.

- 4 Click the **TRANSFER** drop-down and select **DMS**.
- 5 If the transfer is successful, the Order Transfer window will be displayed.

If you click **No**, the connection with the DMS will be retained. If you click **Yes**, you will delete the order from Microcat EPC, and you will be logged out of the DMS.



The screenshot shows the 'Order Transfer' dialog box with the following content:

- Order Status: Order transferred successfully.
- Message from DMS: The order is now complete.
- Order ID: RO12345
- Do you want to delete the Order?
- Buttons: **NO** and **YES**

If the order transfer was successful but is still pending, further action may be required directly in the DMS to finalise the order. If the order failed to transfer, it means there is an issue with the order that will need to be resolved.

Set up DMS integration with Superservice Menus

Once the DMSi has been installed, you can set up a DMS connection in the DMSi and configure the integration settings within Superservice Menus.

Depending on the connection type you select when you log in, Superservice Menus can then exchange data with your DMS and transfer parts and service information to your DMS.


Set up a new DMS connection

The Infomedia DMSi allows you to add either preconfigured or customised DMS connections.

Add a preconfigured DMS connection

If the settings for your preferred DMS connection have been automatically preconfigured in the DMSi, the DMS connection will be available in the Preconfigured connections frame.


To add a preconfigured DMS connection:


- 1 Right-click the **DMSi** icon  on the Windows taskbar and select **Settings**.
- 2 Click **Add New**.
- 3 Select **Superservice Menus - All Franchises** from the **Select application** drop-down.
- 4 Select your DMS from the **Use a preconfigured connection** drop-down and click **OK**.
- 5 Double-click on your new DMS connection in the **Available Connections** frame.
- 6 Click **Settings** and confirm details or make changes, as required.
- 7 Click **OK**.

Add a custom DMS connection

The Infomedia DMSi allows you to add customised DMS connections.

To add a custom connection for a web services-based DMS:

- 1 Right-click the  icon on the Windows taskbar and select **Settings**.
- 2 Click **Add New**.
- 3 Select **Superservice Menus - All Franchises** from the **Select application** drop-down.
- 4 Click **Add New** in the **Set up a custom connection** frame.
- 5 Select **Integrate with a Web-Services-based DMS** and click **Next**.
- 6 In the **General** tab, the web services settings must be specified.
By default, **FCSD-E** will be selected automatically as the provider.
- 7 Enter the **DMS Name**, **URL** and **URN** in the **Provider Settings** fields.



New DMS Configuration Wizard

Web Services Settings
Please select your Web Services settings.

General

Select Provider
FCSD-E

Provider Settings

DMS Name
Ford DMS


URL
http://localhost:7070/axis/services

URN
DMSServer

Test Connection

Back Next Cancel

The information can be copied from Ford eCat (**More** → **Settings** → **Administration tab** → **DMS Server**) or supplied by the Dealer Service Provider (DSP).




Set DMS Parameters

URL

URN


- 8 Click **Test DMSi Connection** to ensure a successful connection with the DMSi.
If you are unable to connect, check your settings.
- 9 Once your settings are complete, click **Next**.

- 10 Confirm the name or type a new name for the DMS connection and click **Finish**.
By default, the DMS name entered in the Provider Settings will be displayed.



- 11 Click **OK**.

The new DMS connection will be displayed in the Available Connections panel of the Integration Settings window in the DMSi.



- ▶ To check your DMSi settings at any time, right-click the Infomedia DMSi 8  icon on your Windows taskbar and select **Settings**.
- ▶ For information on installing the DMSi on a server, refer to the DMSi Server Installation Guide for Superservice Menus.

Configure the DMSi Integration Settings


Once the DMSi is installed, you need to check and configure the DMSi settings within Superservice Menus.

All DMSi connections will be displayed in the Available Connections drop-down in the Integration Settings screen within Superservice Menus. You must confirm that the required connection is selected.


To set up the DMSi integration within Superservice Menus:

- 1 Access Superservice Menus and click the  icon.
- 2 Select **Integration Settings** and click **Edit**.
- 3 Click the **New DMSi Application** icon  to activate the new DMSi.
- 4 Select **Local** from the **Integration Type** drop-down.
- 5 Select your DMS connection from the **Available Connections** drop-down.
If you have multiple DMS connections, you must select the required connection.
- 6 Enter your DMS user name and password.

Your DMS credentials are different from your Superservice Menus credentials.



The screenshot shows the 'Integration Settings' screen. At the top right, there are buttons for 'Cancel', 'Save', 'Add DMS', and 'Add Third Party'. Below these, the 'Integration Type' is set to 'DMSi'. The 'New DMSi Application' section has a 'Yes' button. The 'Integration Type' is set to 'Local'. The 'Available Connections' is set to 'Superservice Menus All Franchi...'. The 'User Name' field contains 'jsmith' and the 'Password' field is masked with asterisks. The 'Automatic Logon' checkbox is checked. Under 'LON Type for DMS Integration', the 'LON14' radio button is selected. At the bottom, there are 'Test DMSi Connection' and 'Advanced' buttons.

- 7 Select the **Automatic Logon** checkbox.
If the checkbox is not selected, you will be prompted to enter the DMS credentials each time you logon.
- 8 Select the required **LON Type for DMS integration**.
- 9 Click **Save**.
- 10 Click  to ensure a successful connection with the DMSi.
When you select your connection, an automatic test is performed.

Log in to the DMS

Once your settings are complete, you can log in to the DMS from Superservice Menus. You will then need to select a connection type. There are three types of connection to the DMS.

Connection Type 1 - Default

- This connection type uses no customer or vehicle information from the DMS. The vehicle is selected within Superservice Menus.
- It allows you to only look up the labour information for an operation from the DMS.
- This connection type does not allow you to transfer an order to the DMS.


Connection Type 2 - Current DMS Session

- This connection type uses customer or vehicle information from an open session within the DMS.
- The list of results will be displayed, allowing you to select one.
- The information about the selected customer and vehicle will be loaded.
- This connection type allows you to transfer an order to the DMS.

Connection Type 3 - SSM Session

- This connection type allows you to search the DMS for customer or vehicle information.
- The list of results will be displayed, allowing you to select one.
- The information about the selected customer and vehicle will be loaded.
- This connection type allows you to transfer an order to the DMS.

To log on to the DMS and select the connection type:

- 1 Click the  icon on the status bar.
When successfully connected, the DMS icon will display as green.
- 2 Select your connection type and click **Connect**:
 - **Default (No Parameters)**: There is no further action for this option.
 - **Current DMS Session**: After you click Connect, a list of your current open sessions will be displayed.
 - **SSM Session**: Enter your search criteria, such as the customer name or VIN, to perform a search on the DMS. If any customer details are already loaded, they will automatically populate the customer or vehicle information.

DMS Connection Type ×

Please select a DMS connection type:

1. Default (No Parameters)
 2. Current DMS Session
 3. SSM Session

- 3 Select the customer record that you want from the list (if required).
The customer and vehicle information will be loaded.

View DMS pricing options

For service or labour menus, you will be able to view the DMS pricing options and the available SSM price options. By default, the DMS retail price will be selected. For parts added to an order, the DMS pricing details will be displayed.

If the Current DMS Session or the Microcat EPC Session connection types were selected, then the customer-specific pricing will also be shown (if available).

Transfer service information to the DMS

If the Current DMS Session or the Microcat EPC Session connection types were selected, you can transfer parts or service information from Superservice Menus to your DMS.


To transfer parts and service information to your DMS:

- 1 Start your DMS.
- 2 In your DMS, open the order that you want to transfer the data to.
- 3 In Superservice Menus, select a service operation or repair.
- 4 View the DMS retail pricing on the quote.
- 5 Select a different price level from the **Price Type** drop-down (if required).



The image shows a dropdown menu with the label 'Price Type' in blue. The selected option is 'DMS - Technical - Retail' in blue text. A small downward arrow is visible to the right of the text.


To display the default Superservice Menus pricing, select **Technical** in the **Price Type** drop-down.

- 6 After you have selected the correct price level, click **Add to Quote**.
- 7 Confirm the details of the quote.
- 8 Click the  drop-down, select **Transfer**, and then select **DMSi**.

The parts and service information will be transferred to your DMS.

Manage integration settings

DMS connections are maintained in the Integration Settings window. Multiple DMS connections can be set up and will be displayed in the Available Connections frame.

To access the Integration Settings window, right-click the **DMSi** icon  on the Windows taskbar and select **Settings**.

Delete a connection

Connections that are no longer required can be deleted.

To delete a connection:

- 1 Select the required DMS connection.
- 2 Click **Delete**.
- 3 Click **OK** to confirm the deletion.

Edit a connection

Existing DMS connections, including preconfigured connections, can be edited as required.

To edit an existing connection:

- 1 Select the required DMS connection.
- 2 Click **Settings**.

The configuration settings that were selected when the connection was created will be displayed.

- 3 Amend the settings in each tab as required and click **OK**.

Export or import a connection

DMS connections can be exported or imported in an .xml format. This enables DMS connections to be shared across different users.

To export a connection:

- 1 Select the required DMS connection.
- 2 Click **Export**.
- 3 Specify a location to save the file to and click **Save**.

The DMS connection will be written to an .xml file at the specified location.

To import a connection:

- 1 Click **Add New**.
- 2 Select from the **Application** drop-down.
- 3 Click **Import XML**.
- 4 Navigate to the .xml file that contains the DMS connection.

INFOMEDIA™